



aquarius
SOFTWARE

LICENCIAMIENTO DE SOFTWARE GE

MÁQUINAS FÍSICAS ONLINE

Departamento Técnico



CONSIDERAÇÕES INICIAIS


Neste cenário, o computador com softwares GE a serem licenciados está conectado à internet. As licenças são baixadas diretamente do servidor de licenças da GE (Cloud License Server) para o computador.



Antes de começar o procedimento, certifique-se que a licença a ser usada durante o processo foi retornada para o servidor de licenças da GE e não está em uso. Para saber como devolver as licenças para o servidor GE acesse o [site da Aquarius](#).


Instalação do Software de Licenciamento

1. Feche todos os softwares GE em execução nos computadores.
2. Remova hardware keys conectadas aos computadores.
3. Faça o download do instalador da última versão do Common Licensing a partir de nosso Sharepoint: [link para download](#)
4. Execute o instalador como administrador (clique com botão direito > Executar como administrador).
5. Selecione a opção **Install License Client**.
6. Siga as instruções apresentadas para realizar a instalação do software.




Ativação das Licenças

Caso já tenha o License Client instalado, certifique-se que a versão é a mais atual. Na dúvida, basta encaminha e-mail para: suporte@aquarius.com.br




ATENÇÃO: se esta ativação estiver sendo feita em uma máquina virtual online, consulte o documento apropriado de licenciamento de [máquinas virtuais online](#).

1. : Inicie o License Client, assegurando-se de que está conectado à internet (o símbolo de nuvem na parte inferior direita da janela deve estar como na figura abaixo).
2. Vá à guia “**Activate Licenses**” e clique opção 1 “**Yes, for this computer from the GE Cloud License Server**”.



- 1 Yes, for this computer from the GE Cloud License Server ←
- 2 Yes, for this computer from a local license server
- 3 Yes, for the inserted Hardware Key ?

3. Digite ou copie e cole os códigos de ativação, encontrados no arquivo que foi enviado no CD ou no e-mail pela Aquarius Software, após preencher todos os campos, clique no botão “**Add Code**”. Vários códigos podem ser inseridos de uma vez.



License Client

View Licenses **Activate Licenses** Return Licenses Complete Offline Process Advanced


Activate licenses from the GE cloud server

Enter your activation code(s): - - -

Activation Codes:

© 2020 General Electric Company. All Rights Reserved. Version: 19.2.1725.0

4. Quando todos os códigos de ativação estiverem na lista "Activation Codes", clique no botão "Activate".



License Client

View Licenses **Activate Licenses** Return Licenses Complete Offline Process Advanced


Activate licenses from the GE cloud server

Enter your activation code(s): - - -

Activation Codes:

© 2020 General Electric Company. All Rights Reserved. Version: 19.2.1725.0

5. Se os códigos estiverem corretos, você será redirecionado para a aba de visão geral das licenças.



The screenshot shows the 'License Client' application window. The title bar reads 'License Client'. The main menu includes 'View Licenses', 'Activate Licenses', 'Return Licenses', 'Complete Offline Process', and 'Advanced'. A blue banner at the top displays 'AQUARIUS SOFTWARE L licenses on this computer' with a key icon. Below this, a summary box provides the following information:

Customer Service Number: 12176400	Creation Date: 21 out 2020	License Source: GE Software License
Device Id: RUXBTDR0100X	Expiration Date: 21 out 2021	License Type: Device Locked

The interface is divided into two main sections: 'Your Licensed Products' and 'License Information'. 'Your Licensed Products' lists: Batch Execution, CIMPLICITY, ControlST, CSense, Dream Reports, Drivers, and GE SmartSignal. A 'Show All Products' link is visible at the bottom of this list. 'License Information' is currently displaying details for 'Batch Execution' (Sales Demo License). The details include:

License Expiration	No Expiration
Number of Phases Licensed	255
Number of Units Licensed	255
Licensed Version	5.6

Under the 'Options' section, 'Electronic Signatures' is shown as 'Enabled'. A 'Refresh Data' button is located at the top right of the License Information section. The footer of the application shows '© 2020 General Electric Company. All Rights Reserved.' and 'Version: 19.2.1725.0'.